


# Cluster Wheel Vehicle Switch




## A. Extrude1.

Step 1. Click File Menu > New, click **Part Metric**  and OK.

Step 2. Click **Top Plane**  in the Feature Manager and click **Sketch**  on the context toolbar, **Fig. 1**.

Step 3. Click **Center Rectangle**  in the **Rectangle flyout**  on the Sketch toolbar.




**Fig. 1**

Step 4. Sketch a **centerpoint rectangle at Origin** , **Fig. 2**.

Step 5. Click **Centerline**  in the **Line flyout**  on the Sketch toolbar.

Step 6. Sketch **vertical centerline from Origin** , **Fig. 3**.




**Fig. 2**

Step 7. Click **3 Point Arc**  (S) in the **Arc flyout**  on the Sketch toolbar.


Step 8. Sketch **arc across top and bottom lines with arc tangent**  with left line, **Fig. 4**.

Step 9. **Unselect Arc tool**. To unselect, right click graphics area and click **Select**  from menu.


Step 10. **Ctrl click arc endpoints** to select both. Release Ctrl key and click **Make Vertical**  on the context toolbar, **Fig. 5**.



**Fig. 3**



**Fig. 4**




**Fig. 5**

Step 11. Click **Smart Dimension**  (S) on the Sketch toolbar.



Step 12. Add dimensions, **Fig. 6**.

Step 13. **Unselect Smart Dimension**. To unselect, right click graphics area and click **Select**  from menu.




Step 14. **Ctrl click arc and centerline** to select both, **Fig. 7**.

Step 15. Click **Mirror Entities**  on the Sketch toolbar, **Fig. 8**.



Step 16. Click **Features**  on the Command Manager toolbar.

Step 17. Click **Extruded Boss/Base**  on the Features toolbar.

Step 18. In the Boss-Extrude Property Manager set:

under Direction 1, **Fig. 9**


End Condition **Blind**

Depth  4

under Selected Contours

click the **contour**, **Fig. 10**

click OK .




**Fig. 9**

## B. Save as "SWITCH".

Step 1. Click File Menu > Save As.


Step 2. Key-in **SWITCH** for the filename and press ENTER.



**Fig. 10**

## C. Extrude2.

Step 1. Click the **top face** and click **Sketch**  on the context toolbar, **Fig. 11**.



Step 2. Click **Circle**  (S) on the Sketch toolbar.


Step 3. Sketch circle at Origin , **Fig. 12**.

Step 4. Click **Smart Dimension**  (S) on the Sketch toolbar.

Step 5. Dimension **diameter 7**, **Fig. 12**.

Step 6. Click **Features**  on the Command Manager toolbar.


Step 7. Click **Extruded Boss/Base**  on the Features toolbar.




Step 8. In the Boss-Extrude Property Manager set:  
under Direction 1, **Fig. 13**  
End Condition **Blind**

**Depth**  **2**  
click OK .

Step 9. Save  (Ctrl-S).



**Fig. 13**




**Fig. 14**

## D. Extrude3.

Step 1. Click the **top face of Extrude2** and click **Sketch**



on the context toolbar, **Fig. 15**.




Step 2. Click **Circle**  (S) on the Sketch toolbar.

Step 3. Sketch circle at Origin , **Fig. 16**.

Step 4. Click **Smart Dimension**  (S) on the Sketch toolbar.

Step 5. Dimension **diameter 4.4**, **Fig. 16**.

Step 6. Click **Features**  on the Command Manager toolbar.


Step 7. Click **Extruded Boss/Base**  on the Features toolbar.

Step 8. In the Boss-Extrude Property Manager set:  
under Direction 1, **Fig. 17**  
End Condition **Blind**


**Depth**  **1.8**

click OK .


Step 9. Save  (Ctrl-S).



**Fig. 17**



**Fig. 16**



**Fig. 18**

## E. Fillet Edge.

Step 1. Click **Fillet**  on the Features toolbar.

Step 2. In the Fillet Property Manager set:  
select **FilletXpert**, **Fig. 19**

**Radius**  **.5**  
click **top circular edge**  
click **OK** .

Step 3. Save  (Ctrl-S).




Fig. 20




Fig. 19

## F. Appearance: Gray Plastic.

Step 1. Click part, click **Appearance Callout**  on the context toolbar and click **SWITCH** , **Fig. 21**.

Step 2. In the Appearances Task pane, expand **Plastic**, click **Medium Gloss** and in the lower pane select **light gray medium gloss plastic**, **Fig. 22**.

Step 3. Save  (Ctrl-S).

Click part




Fig. 21




Fig. 24




Fig. 22





Fig. 23

## G. Open CWV Assembly File.

Step 1. Open your CWV Assembly file.

Step 2. Click **Trimetric**  on the Standard Views toolbar.


Step 3. **Isolate the Chassis**  component, **Fig. 25**. To Isolate, Right click **Chassis** in the Feature Manager. **Right click** and click **Isolate** from the menu.



## H. Insert Switch.

Step 1. Click **Insert Components**  on the Assembly toolbar.


Step 2. Browse, Open Switch and place, **Fig. 26**.




## I. Mate: Switch.

Step 1. Click **Right Plane**  in the Feature Manager and **Mate**  on the context toolbar, **Fig. 27**.


Step 2. Expand the flyout Feature Manager design tree, expand **Switch** and click **Right Plane** , **Fig. 28**.



**Fig. 27**



**Fig. 28**



**Fig. 29**

Step 3. Click **top face of Extrude1 of Switch** and **front face of Chassis**, **Fig. 30**.

Step 4. Click **Distance**  and **Flip Mate Alignment**  in Mate pop-up, **Fig. 31**. Set **distance .8** and press ENTER. The Switch should be positioned just inside the front of Chassis, **Fig. 30**. If positioned in opposite direction, click **Flip Dimension**  in the Mate pop-up. Click **Add/Finish Mate**  to add Distance mate.




Fig. 30



Fig. 31

Step 5. Click **top face of Switch** and **bottom front edge of Chassis**, **Fig. 32**.

Step 6. Click **Distance**  in Mate pop-up, **Fig. 33**. Set **distance 13** and press ENTER. The Switch is now fully inside the Chassis, **Fig. 34**. If positioned in opposite direction, click **Flip Dimension**  in the Mate pop-up. Click **Add/Finish Mate**  to add Distance mate.




Fig. 32



Fig. 33

Step 7. Click **OK**  in the Property Manager.

Step 8. Save  (Ctrl-S).





Fig. 34

## J. Indent Switch into Chassis.


Step 1. Click **Chassis**  component in the Feature Manager and click **Edit Part**  on the context toolbar, **Fig. 35**.


Step 2. Click Insert Menu > Features > Indent.

Step 3. In the Indent Property Manager:  
 under Selections, **Fig. 36**  
 Target body:  
 click **Chassis**, **Fig. 37**  
 Tool body region:  
 click **Switch**  
 check **Cut**  
 under Parameters  
**Clearance .13**  
 click OK .




**Fig. 36**

Step 4. Click **Edit Component**  on the Features toolbar to exit.

Step 5. **Exit Isolate**. To Exit, click **Exit Isolate**  on the Isolate pop-up toolbar, **Fig. 38**.


Step 6. Save All  (**Alt-F L**).



**Fig. 37**



**Fig. 38**



**Fig. 39**